

User's Guide

mmWave Demo Visualizer



ABSTRACT

This user's guide presents the TI Gallery app – [mmWave Demo Visualizer](#) – for configuring mmWave sensors and visualizing point cloud objects generated by the [mmWave SDK demo](#). The mmWave Demo Visualizer app is meant to be used in conjunction with the mmWave SDK demo running on the TI EVM for mmWave devices. The app can also be reached at the [TI Gallery website](#) – search for mmWave_Demo_Visualizer. The mmWave Demo Visualizer app is browser-based and can be run on any PC operating system (Windows®, Linux®, or macOS®), and TI recommends running the app using the Chrome® browser for the best plotting performance.

Table of Contents

1 Setup Instructions	3
1.1 Browser Setup (First Time Only).....	3
1.2 mmWave Device Setup.....	3
1.3 Serial Port Setup.....	3
2 CONFIGURE Tab	4
2.1 Platform.....	4
2.2 SDK Version.....	4
2.3 Antenna Config (Azimuth Resolution - Degrees).....	4
2.4 Processing Chain.....	5
2.5 Desirable Configuration.....	5
2.6 Frequency Band (GHz).....	5
2.7 Scene Selection – Best Range Resolution.....	5
2.8 Scene Selection – Best Velocity Resolution.....	6
2.9 Scene Selection – Best Range.....	7
2.10 Plot Selection.....	8
2.11 User Selected Configuration.....	9
3 PLOTS Tab	11
3.1 X-Y Scatter Plot.....	11
3.2 Doppler Range Plot.....	12
3.3 Range Profile.....	12
3.4 CPU Load.....	14
3.5 Range-Doppler Heatmap.....	15
3.6 Range-Azimuth Heatmap.....	16
3.7 3-D Scatter Plot.....	17
3.8 Display Parameters.....	17
3.9 Real-Time Tuning.....	19
3.10 Advanced Commands.....	20
3.11 Plot Settings.....	21
4 Advanced Options	21
4.1 Load Configuration From PC.....	21
4.2 Getting the Version.....	21
4.3 RCS.....	22
4.4 Concurrent Recording of Processed Stream From mmWave Device.....	22
5 Troubleshooting	23
5.1 Console Message: Errors Returned by Device.....	23
5.2 Serial Port Status Message: Not Switching to Hardware Connected or Both Ports Are Not Showing Up.....	23
5.3 Console Message: sensorStart Message Not Sent to Host.....	23
5.4 Warning for Plots and Frame Rate.....	23
5.5 Configuration Successful, but Plots Not Updating.....	24
6 Customizing the mmWave Demo Visualizer	24
Revision History	24

List of Figures

Figure 1-1. TI Cloud Agent Installation (First Time Setup).....	3
Figure 1-2. Device Manager Ports.....	3
Figure 1-3. Serial Port Configuration in App.....	4
Figure 1-4. COM Port Status When Correct Ports Are Configured.....	4
Figure 1-5. COM Port Status When Ports Are Not Connected.....	4
Figure 2-1. Valid Configuration.....	10
Figure 3-1. X-Y Scatter Plot for Detected Objects.....	11
Figure 3-2. Doppler Range Plot for Detected Objects.....	12
Figure 3-3. Range Profile in Linear Scale.....	13
Figure 3-4. Range Profile in Log Scale.....	13
Figure 3-5. Range and Noise Profile in Log Scale.....	13
Figure 3-6. CPU Load for Frame Rate = 30 fps (Example).....	14
Figure 3-7. Doppler Range Heatmap.....	15
Figure 3-8. Azimuth-Range Heatmap (Example).....	16
Figure 3-9. 3-D Scatter Plot.....	17
Figure 3-10. Display Parameters – Profiling.....	18
Figure 3-11. Display Parameters – Scene.....	18
Figure 3-12. Display Parameters - Chirp/Frame.....	19
Figure 3-13. Range Peak Grouping Disabled (Left) and Enabled (Right).....	20

Trademarks

Code Composer Studio™ is a trademark of Texas Instruments.
 Windows® is a registered trademark of Microsoft Corporation.
 Linux® is a registered trademark of Linus Torvalds.
 macOS® is a registered trademark of Apple, Inc.
 Chrome® is a registered trademark of Google, Inc.
 All trademarks are the property of their respective owners.

1 Setup Instructions

1.1 Browser Setup (First Time Only)

If this is your first time using this app, you may be prompted to install a browser extension and the TI Cloud Agent Application (see [Figure 1-1](#)).




Figure 1-1. TI Cloud Agent Installation (First Time Setup)

1.2 mmWave Device Setup

Follow the instructions in the MMWAVE-MCUPLUS-SDK User Guide to run the mmWave demo and connect to the PC where the app will be running.

1.3 Serial Port Setup

Follow the first-time setup instructions previously described before following the steps here.

1. If the mmWave device is connected by the USB cable to the PC running this app, then you can locate the following COM ports using the Device Manager on a Windows PC (see [Figure 1-2](#)).
 - a. XDS110 Class Application/User UART → This is the port where the CLI (command line interface) runs for all the various demos. This port is called the CFG_port.
 - b. XDS110 Class Auxiliary Data port → This is the port on which binary data generated by the processing chain in the mmWave demo will be received by the PC. This binary data contains the detected object list and its properties (range, Doppler, angle, and so on). This port is called the visualization port or Data_port.




Figure 1-2. Device Manager Ports

2. In the browser app, navigate to Menu → Options → Serial Port and set up the COM ports in the pop-up window as follows (see [Figure 1-3](#)).
 - a. CFG_port: Use the COM port number for *XDS110 Class Application/User UART* and set Baud: 115200
 - b. Data_port: Use the COM port *XDS110 Class Auxiliary Data Port* and set Baud: For SDK version ≤ 4.3, 892857 for AM273X and 852272 for AWR294X For SDK version ≥ 4.4, 3125000 for both AM273X and AWR294X. This needs to be set by selecting "custom" in the Baud Rates drop down and setting the desired value (max: 3125000). Note that the sensor should be in stopped or rebooted state for the changes to take effect. Visualizer communicates with the sensor over CLI port to configure it to the user provided baud rate in this dialog box




Figure 1-3. Serial Port Configuration in App

3. Click the CONFIGURE button and the control should go back to the main browser window.
4. At this point, the app automatically tries to connect to the target (mmWave Sensor), see [Figure 1-4](#).



Figure 1-4. COM Port Status When Correct Ports Are Configured

5. If the app does not connect to the CFG_port or the connection fails, try to connect to the target by clicking in the bottom-left corner of the app (see [Figure 1-5](#)). For mmWave SDK 3.3 and earlier, DATA_port will show connected only after the sensor is configured and sending detected objects. For mmWave SDK 3.4 and later, both CFG_port and DATA_port will show connected if the ports are valid .




Figure 1-5. COM Port Status When Ports Are Not Connected

2 CONFIGURE Tab

This tab allows users select the parameters for configuring the mmWave device. In this document, the subsection numbers dictate a certain sequence of programming so that precedent parameters are set first followed by dependent parameters. Users can follow any sequence in configuring the settings, but note that certain knobs, sliders, and drop-downs influence the values of other dependent parameters, and you may have to readjust dependent parameters to obtain the desired selection.

2.1 Platform

This is a drop-down menu that prompts users to select the correct mmWave device to which the app is connected to through the serial port. If you are trying to just *save config to PC*, then select the mmWave device for which the desired configuration must generate.

2.2 SDK Version

This is a drop-down menu that prompts users to select the matching SDK version as the one running on the mmWave device. If the version does not match, then the GUI prompts an error when using the *Send Config to mmWave Device* button or *Load config from PC and send* button. However, there is no such check done when using the *Save config to PC* button, and users can choose the SDK version for which the compatible configuration should be generated.

2.3 Antenna Config (Azimuth Resolution - Degrees)

This is a drop-down menu that prompts users to select the azimuth resolution and elevation configuration for TI mmWave EVMs. The options for setting the azimuth resolution depends on the antenna layout on the EVMs

Effects on other user knobs:

- Affects the possible minimum and maximum values for all sliders in the *scene selection*.
- When elevation is selected, the *Scatter Plot* selection results in a 3D plot in the plots tab.

CLI command details: defines RX and TX antenna mask in the channelCfg command and creates the chirpCfgs.

Note

Users must reboot the mmWave device when switching between options in this menu.

2.4 Processing Chain

This is a drop-down menu that prompts users to select the matching "Processing Chain" as the one running on the mmWave device. If the processing chain does not match, then the GUI prompts an error when using the *Send Config to mmWave Device* button or *Load config from PC and send* button. However, there is no such check done when using the *Save config to PC* button, and users can choose the "Processing Chain" for which the compatible configuration should be generated.

Note

Users must reboot the mmWave device when switching between options in this menu.

2.5 Desirable Configuration

This is a drop-down menu that prompts users to select the parameter that they are most concerned about, to tune the system resources towards that configuration. For more details, see [Section 2.7](#). When the user selects a value in this menu, all the sliders, text boxes, checkboxes, and drop-downs (except for Platform) get reset to their default values (equivalent to pressing a Reset Selection button).

2.6 Frequency Band (GHz)

This is a drop-down menu that prompts users to select the frequency band of operation. The mmWave sensors support two choices: wide band (4 GHz spanning 77 to 81 GHz/60 to 64 GHz) and narrow band (1 GHz spanning 76 to 77 GHz).

CLI command details: defines the start frequency in GHz in the profileCfg command.

2.7 Scene Selection – Best Range Resolution

This section guides users through the sequence of selections they should follow when Best Range Resolution is selected under the Desirable Configuration menu.

2.7.1 Frame Rate (fps)

This is a slider that prompts users to select the rate at which the measurement data must be shipped out of the mmWave device.

Effects on other user knobs:

- Controls the minimum value on the Maximum Radial Velocity slider.
- Faster rates limit the number of plots and measurement data that can be captured from the mmWave device. For more details, see [Section 2.10](#).

CLI command details: defines frame duration (frame periodicity in ms) in the frameCfg command.

2.7.2 Range Resolution (m)

This is a slider that prompts users to select the desired range resolution in meters. Select the value based on the minimum amount of separation you expect between the detected objects or points in the point cloud. Because this is the Best Range Resolution configuration, the slider presents options only for the best possible range resolution for the user-selected frequency band.

Effects on other user knobs:

- Relatively lower or finer Range Resolution selected by this slider provides options for longer Max Unambiguous Range but lower values for Maximum Radial Velocity.
- Relatively higher or coarser Range Resolution selected by this slider provides options for shorter Max Unambiguous Range but higher values for Maximum Radial Velocity.

This slider allows for minor tweaking in the centimeter units, to help users attain desired fine tuning of configuration for the Max Unambiguous Range and Maximum Radial Velocity.

CLI command details: defines frequency slope constant and Ramp end time in μs in the profileCfg.

2.7.3 Maximum Unambiguous Range (m)

This is a slider that prompts users to select the desired Maximum Unambiguous Range in meters. Select the value based on the farthest distance you expect to see objects detected. To understand the Radar cross section and the actual range at which objects equal to the radar cross section can be theoretically detected by mmWave technology, see [Section 4.3](#).

Effects on other user knobs:

- Setting this slider to lower values provides more options for the Radial Velocity Resolution, versus setting this slider to higher values providing less options for the Radial Velocity Resolution.

CLI command details: defines number of ADC samples and ADC sampling frequency in ksp/s in the profileCfg command.

2.7.4 Maximum Radial Velocity (m/s)

This is a slider that prompts users to select the desired Maximum Radial Velocity in meters/second. Select the value based on the maximum radial velocity you expect targets to be moving in within the radar field of view.

Effects on other user knobs:

- Radial Velocity Resolution is directly proportional to the Maximum Radial Velocity setting. Setting this slider to lower values provides finer Radial Velocity Resolution versus setting this slider to higher end of values provides coarser Radial Velocity Resolution.

CLI command details: defines idle time in μs in the profileCfg command.

2.7.5 Radial Velocity Resolution (m/s)

This is a drop-down menu that prompts users to select the desired Radial Velocity Resolution in meters/second.

Effects on other user knobs:

- This knob is the lowest dependent parameter in this configuration and gets constrained by all the preceding parameters.

CLI command details: defines number of loops in the frameCfg command

2.8 Scene Selection – Best Velocity Resolution**2.8.1 Frame Rate (fps)**

This is a slider that prompts users to select the rate at which measurement data must be shipped out of the mmWave device.

Effects on other user knobs:

- As the Best Velocity Resolution configuration, it controls the Radial Velocity Resolution, and sets it to the best possible value for the chosen frame rate.
- Controls the minimum value on the Maximum Radial Velocity slider.
- Faster rates limit the number of plots and measurement data that can be captured from the mmWave device. For more details, see [Section 2.10](#).

CLI command details: defines frame duration (for example, frame periodicity in ms) in the frameCfg command.

2.8.2 Radial Velocity Resolution (m/s)

As a Best Velocity Resolution configuration, the Radial Velocity Resolution is set to the best possible value for the chosen frame rate.

2.8.3 Maximum Radial Velocity (m/s)

This is a slider that prompts users to select the desired Maximum Radial Velocity in meters/second. Select the value based on the maximum radial velocity you expect the targets to be moving in within the radar field of view.

Effects on other user knobs

Based on the system resources diverted to fulfill the user-selected value for Maximum Radial Velocity, options for Range Resolution are affected in this configuration.

- Higher values for Maximum Radial Velocity selected by this slider provides only coarser options for Range Resolution and short-range options for Max Unambiguous Range.
- Lower values for Maximum Radial Velocity selected by this slider provides more finer options for Range Resolution and long-range options for Max Unambiguous Range.

CLI command details: defines the number of loops in the frameCfg command.

2.8.4 Range Resolution (m)

This is a slider that prompts users to select the desired range resolution in meters. Select the value based on the minimum separation you expect between the detected objects or points in the point cloud.

Effects on other user knobs:

- Relatively lower or finer Range Resolution selected by this slider provides options for shorter Max Unambiguous Range.
- Relatively higher or coarser Range Resolution selected by this slider provides options for longer Max Unambiguous Range.

CLI command details: Range Resolution and Max Unambiguous Range define the number of ADC samples, frequency slope constant, Ramp end time in μs , idle time in μs , and ADC sampling frequency in ksp/s in the profileCfg command.

2.8.5 Maximum Unambiguous Range (m)

This is a slider that prompts users to select the desired Maximum Unambiguous Range in meters. Select the value based on the farthest distance you expect to see objects detected. To understand the radar cross section and the actual range at which objects equal to the radar cross section can be theoretically detected by mmWave technology, see [Section 4.3](#).

Effects on other user knobs:

- Moving this slider fine-tunes the user-selected Range Resolution value.

CLI command details: Range Resolution and Max Unambiguous Range define the number of ADC samples, frequency slope constant, Ramp end time in μs , idle time in μs , and ADC sampling frequency in ksp/s in the profileCfg command.

2.9 Scene Selection – Best Range

2.9.1 Frame Rate (fps)

This is a slider that prompts users to select the rate at which measurement data must be shipped out of the mmWave device.

Effects on other user knobs:

- Controls the minimum value on the Maximum Radial Velocity slider.
- Faster rates limit the number of plots and measurement data that can be captured from the mmWave device. For more details, see [Section 2.10](#).

CLI command details: defines the frame duration (for example, frame periodicity in ms) in the frameCfg command.

2.9.2 Maximum Unambiguous Range (m)

This is a slider that prompts users to select the desired Maximum Unambiguous Range in steps of 5 meters. Select the value based on the farthest distance you expect to see objects detected. See [Section 4.3](#) to understand the radar cross section and the actual range at which objects equal to the radar cross section can be theoretically detected by mmWave technology.

Effects on other user knobs:

- Setting this slider to lower values provides less but finer options for Range Resolution, versus setting this slider to higher values providing more but coarser options for the Range Resolution.

CLI command details: defines the frequency slope constant in the profileCfg command.

2.9.3 Range Resolution (m)

This is a slider that prompts users to select the desired range resolution in meters. Select the value based on the minimum amount of separation you expect between the detected objects or points in the point cloud.

Effects on other user knobs:

- Coarser values for Range Resolution selected by this slider provides more options and higher values for Maximum Radial Velocity.
- Finer values for Range Resolution selected by this slider provides less options and lower values for Maximum Radial Velocity.

Based on the system resources diverted to fulfill the user-selected value for Range Resolution, options for Maximum Radial Velocity are affected in this configuration.

CLI command details: defines the number of ADC samples, Ramp end time in μs , and ADC sampling frequency in ksp/s in the profileCfg command.

2.9.4 Maximum Radial Velocity (m/s)

This is a slider that prompts users to select the desired Maximum Radial Velocity in meters/second. Select the value based on the maximum radial velocity you expect the targets to be moving in within the radar field of view.

Effects on other user knobs:

Radial Velocity Resolution is directly proportional to the Maximum Radial Velocity setting. Setting this slider to lower values provides finer Radial Velocity Resolution, versus setting this slider to higher values providing coarser Radial Velocity Resolution.

CLI command details: defines the idle time in μs in the profileCfg command.

2.10 Plot Selection

This section prompts users to select the plots they want to see on the Plots tab. For the best performance, depending on the scene parameters that are selected by the user, selecting more than two plots may require a frame rate around 10 fps. Selecting heatmaps requires the frame rate to be 1-3 fps, otherwise the target (mmWave sensor) will not have enough frame duration to ship out data every frame over the UART.

2.10.1 Scatter Plot

This lets users enable the detected objects list to be sent out by the target (mmWave sensor) device and display it on the Scatter plot and Doppler-Range plot on the plots tab.

CLI command details: defines the detected-objects parameter in the guiMonitor command.

2.10.2 Range Profile

This lets users enable the log-magnitude range profile data at zero Doppler to be sent out by the target (mmWave sensor) device and display it on the Range Profile plot on the plots tab.

CLI command details: defines the log-magnitude range parameter in the guiMonitor command.

2.10.3 Noise Profile

This lets users enable the log magnitude noise profile data to be sent out by target (mmWave sensor) device and display it on the Noise profile graph (green color) in the same Range Profile plot window on the plots tab.

CLI command details: defines the noise profile parameter in the guiMonitor command.

2.10.4 Range Azimuth Heat Map

This lets users enable the zero Doppler radar cube matrix for all range bins and all antennas to be sent out by the target (mmWave sensor) device and display it on the Range azimuth heatmap plot on the plots tab. This requires the frame rate to be 1 fps otherwise the target (mmWave sensor) will not have enough frame duration to ship out data every frame over the UART.

CLI command details: defines the range-azimuth heat map parameter in the guiMonitor command.

2.10.5 Range Doppler Heat Map

This lets users enable the entire detection matrix to be sent out by the target (mmWave sensor) device and display it on the range-doppler heatmap plot on the plots tab. This requires the frame rate to be 1 fps otherwise the target (mmWave sensor) will not have enough frame duration to ship out data every frame over the UART.

CLI command details: defines the range-doppler heat map parameter in the guiMonitor command.

2.10.6 Statistics

This lets users enable the statistics information to be sent out by the target (mmWave sensor) device and to show the CPU load plot on the plots tab.

CLI command details: defines the statistics parameter in the guiMonitor command.

2.11 User Selected Configuration

When the user has selected the parameters in the previous section, they can now take the following actions.

2.11.1 Send Configuration to mmWave Device

This lets users send the generated configuration (CLI) commands to be sent to the target (mmWave sensor) device. This command operates successfully only if the following are met:

- Valid serial ports have been configured as shown in the setup section.
- Target (mmWave sensor) device is booted up and running the mmWave demo from the same SDK version as selected in the *SDK version* drop down menu.

Users can see the commands echoed back on the Console Messages display with the feedback that is received from the target for every line of commands sent. These console messages are a great help when debugging issues or getting familiar with the CLI commands. A successful execution of this button results in the last command *sensorStart* to be sent to the device and a response *Done* to be received from the device.

Another indication of successful connectivity to the target device is the black status bar on the bottom of the page shows two valid COM ports and the status says Hardware Connected (see [Figure 2-1](#)). After successful execution, users can switch to the Plots tab to view the requested plots.




Figure 2-1. Valid Configuration

If the last two lines in the console messages contain any other lines than these, it means either the device generated an error, the device stopped responding, or the commands did not go through completely and the user must try again. For more details, see [Section 5](#).

2.11.2 Saving Configuration to PC

This lets users save the generated configuration (CLI) commands in a .cfg file on the user's PC. Users can then read and modify this file as per their needs. This file can also later be used to send the configuration to the device using the advanced option Load Config from PC and Send button on the plots tab. For more details on the format and content of this generated file, see the [mmWave MCUPLUS SDK User's Guide](#). The top section of this file contains metadata detailing the settings of the user knobs.

2.11.3 Reset Selection

This lets users reset the sliders, checkboxes, textboxes, and drop-downs to their original reset values, except for the platform drop-down.

3 PLOTS Tab

When users have successfully configured the device using either the *Send Config to mmWave Device* or *Load Config from PC and Send* button, they can begin to see data being plotted on the requested plots. If no data is shown on the plots. For more details, see [Section 5](#).

3.1 X-Y Scatter Plot

This plot shows the detected objects in the X-Y domain (see [Figure 3-1](#)). For the advanced frame, this plot shows the union of points detected in all subframes of a given frame.

Note

Select Scatter Plot in the configure tab and configure the device accordingly to view this plot.

The X- and Y-axis can be controlled using the Range Width and Range Depth text boxes. Use the stop button to stop plotting and then you can change these settings. When the settings are changed, resume plotting using the start button. The maximum value users can select is limited by the Maximum Unambiguous Range achievable by the current configuration.




Figure 3-1. X-Y Scatter Plot for Detected Objects

3.2 Doppler Range Plot

This plot shows the detected objects using the range and Doppler coordinates (see [Figure 3-2](#)). For the advanced frame, this plot shows the union of points detected in all subframes of a given frame.

Note

Select Scatter Plot in the Configure tab and configure the device accordingly to view this plot.

The X-axis can be controlled using the Range Width and Range Depth text boxes. Use the stop button to stop plotting and then you can change these settings. When changed, resume the plotting using the start button. The maximum value users can select is limited by the Maximum Unambiguous Range achievable by the current configuration.




Figure 3-2. Doppler Range Plot for Detected Objects


3.3 Range Profile

This plot shows the range profile at the 0th Doppler (static objects) using the blue line and noise profile (if enabled) using green line (see [Figure 3-5](#)). By default, this graph shows the log values. The detected objects in the 0th Doppler range bin are shown as orange cross marks over the blue Range Profile plot line (see [Figure 3-3](#) and [Figure 3-4](#)). For the advanced frame, this plot shows the range profile for the first subframe, which has this plot enabled in the guiMonitor command (the plot title reflects this subframe number). When the range bias is supplied using the compRangeBiasAndRxChanPhase command, the GUI internally uses the range bias to correct the range in meters, as calculated from rangeldx, shipped by the mmWave device. The range and noise profile sent by the mmWave device is compensated for all the 1D and 2D FFT gains and the incoherent combining gain across the antennas, as per the mmWave demo processing chain, before plotting.

Note

Select Range Profile and Noise Profile in the Configure tab and configure the device accordingly to view this plot.

The linear scale for the Y-axis can be selected by unchecking the Range Profile Log Scale checkbox. The maximum limit for the Y-axis in the linear domain can be selected by the user with the Range Profile Y-max text box. Use the stop button to stop plotting and then you can change these settings. Once the settings are changed, resume plotting using the start button.



Range Depth Range Width
 Range Profile Y max Range Profile Log Scale
SENSOR STOP


File Size Max (MB)
 Record time max (s)
RECORD START

LOAD CONFIG FROM PC AND SEND

Profiling | Chirp/Frame | Scene

Platform	0xa1642
SDK Version	2.1.0.4
Number of Detected Objects	3
Frame stats	
InterChirpProcessingMargin (usec)	3771
InterFrameProcessingMargin (usec)	84511
InterFrameProcessingTime (usec)	3651
TransmitOutputTime (usec)	7154
Active/Interframe CPU Load (%)	3/4

Figure 3-3. Range Profile in Linear Scale



Range Depth Range Width
 Range Profile Y max Range Profile Log Scale
SENSOR STOP

File Size Max (MB)
 Record time max (s)
RECORD START

LOAD CONFIG FROM PC AND SEND

Profiling | Chirp/Frame | Scene

Platform	0xa1642
SDK Version	2.1.0.4
Number of Detected Objects	3
Frame stats	
InterChirpProcessingMargin (usec)	3770
InterFrameProcessingMargin (usec)	84510
InterFrameProcessingTime (usec)	3652
TransmitOutputTime (usec)	7154
Active/Interframe CPU Load (%)	3/4

Figure 3-4. Range Profile in Log Scale



Range Depth Range Width
 Range Profile Y max Range Profile Log Scale
SENSOR STOP

File Size Max (MB)
 Record time max (s)
RECORD START

LOAD CONFIG FROM PC AND SEND

Profiling | Chirp/Frame | Scene

Platform	0xa1642
SDK Version	2.1.0.4
Number of Detected Objects	3
Frame stats	
InterChirpProcessingMargin (usec)	3771
InterFrameProcessingMargin (usec)	84476
InterFrameProcessingTime (usec)	3652
TransmitOutputTime (usec)	13246
Active/Interframe CPU Load (%)	3/4

Figure 3-5. Range and Noise Profile in Log Scale

3.4 CPU Load

This plot displays the CPU load for the data processing chain during the active or chirping section of a given frame/subframe and during the nonactive or interframe/intersubframe section of the frame/subframe (see [Figure 3-6](#)). The CPU load is expressed as a percentage of these active and inactive durations and therefore varies for a given profileCfg, but with a different frame rate. This plot shows the CPU load for the C66x DSP core (where the data path processing happens). For the advanced frame, this plot shows the CPU load for the first subframe, which has this plot enabled in the guiMonitor command (the plot title reflects this subframe number).

Note

Select Statistics in the Configure tab and configure the device accordingly to view this plot.




Figure 3-6. CPU Load for Frame Rate = 30 fps (Example)

3.5 Range-Doppler Heatmap

This plot displays the entire radar cube matrix in Range and Doppler coordinates using the heatmap plot (see [Figure 3-7](#)). For the advanced frame, this plot shows the heatmap for the first subframe which has this plot enabled in the guiMonitor command (the plot title reflects this subframe number). When the range Bias is supplied using the compRangeBiasAndRxChanPhase command, the GUI internally uses the range bias to correct the range in meters, as calculated from rangeldx, shipped by the mmWave device.

Note

Select Range Doppler Heat Map in the Configure tab and configure the device accordingly to view this plot.




Figure 3-7. Doppler Range Heatmap

3.6 Range-Azimuth Heatmap

This plot displays the radar cube matrix for zero Doppler only but across all range bins and all antennas (see [Figure 3-8](#)). For the advanced frame, this plot shows the heatmap for the first subframe, which has this plot enabled in the guiMonitor command (the plot title reflects this subframe number). When the range bias is supplied using the compRangeBiasAndRxChanPhase command, the GUI internally uses the range bias to correct the range in meters, as calculated from rangeldx, shipped by the mmWave device.

Note

Select Range Azimuth Heat Map in the Configure tab and configure the device accordingly to view this plot.




Figure 3-8. Azimuth-Range Heatmap (Example)

3.7 3-D Scatter Plot

This is available only when Elevation is selected in the Scene Selection configuration. This plot displays the detected objects in 3-D space (see [Figure 3-9](#)).

Note

Select Scatter Plot, any Antenna config that has non-zero Elevation resolution in the Configure tab and configure the device accordingly to view this plot.




Figure 3-9. 3-D Scatter Plot

3.8 Display Parameters

This is the informational data presented on the plots tab for user reference. Use the embedded tabs to switch between the type of information that is needed.

3.8.1 Profiling Parameters

When this display tab is selected, the screen shows the following information (see [Figure 3-10](#)).

- Platform: the hexadecimal string that is output by the mmWave sensor device.
- SDK version: the version of the software that is currently running on the mmWave sensor device.
- Number of Detected Objects: a continuously updating field (new measurement every frame) that shows the number of detected objects for a given frame.
- Frame Stats or Stats for Subframe: In the case of advanced frame configuration, this lists the subframes (separated by command) for which the following stats are displayed. In the case of legacy frame configuration, there is only one construct of the frame and the following stats apply for the whole frame.
 - InterChirpProcessingMargin: a continuously updating field (new measurement every frame) that shows the time, in microseconds, that is left in a given (chirp + interchirp) duration after the chirp processing. The field has the value that is the average value across all chirps in a given frame, or values separated by commas which are the average value across all chirps in a given subframe.
 - InterFrameProcessingMargin: a continuously updating field (new measurement every frame) that shows the time, in microseconds, that is left in a given frame/subframe after all the frame/subframe processing is completed.
 - InterFrameProcessingTime: a continuously updating field (new measurement every frame) that shows the time, in microseconds, that was consumed for frame/subframe processing after the active chirps were completed.
 - TransmitOutputTime: a continuously updating field (new measurement every frame) that shows the time, in microseconds, for the requested output (controlled using the selections in the Plot Selection section of the Configure tab) to be shipped out over the UART from the mmWave device to the PC.
 - Active/Interframe CPU Load (%): a continuously updating field (new measurement every frame) that shows the percentage CPU load during active chirping time within the frame/subframe and the interframe/ intersubframe time. These values are also reflected on the CPU Load plot for the frame, or the first selected subframe in the guiMonitor command.

- Temperature Report: This section displays the device temperature report from various temperature sensors. The time shown is number of days/hours/minutes/seconds/milliseconds since the device was powered up.

Profiling	Chirp/Frame	Scene
Platform		2944
SDK Version		4.2.0.0
Number of Detected Objects		7
Frame stats (5)		
...InterChirpProcessingMargin (usec)		0
...InterFrameProcessingMargin (usec)		377842
...InterFrameProcessingTime (usec)		13809
...TransmitOutputTime (usec)		11966
...Active/Interframe CPU Load (%)		52/52
Detailed Temperature Report		@time=0 days 00:07:41.473
...@Rx channels (Deg C)		44C, 45C, 46C, 46C
...@Tx channels (Deg C)		47C, 47C, 47C
...@Pm, @Dig0, @Dig1 (Deg C)		44C, 47C, 0C

Figure 3-10. Display Parameters – Profiling

3.8.2 Scene Parameters

When this display tab is selected, the scene parameters are calculated back from the actual configuration that was sent to the device (see [Figure 3-11](#)). These values should approximately match the Configure tab values if the *Send config to MMwave device* button was used to configure the device. In the case of advanced configuration, the values for the different subframes are shown separated by commas for each of the fields.

Profiling	Chirp/Frame	Scene
Range resolution (m)		0.0436
Max Unambiguous Range (m)		8.9297
Max Radial Velocity (m/s)		1.0018
Radial Velocity Resolution (m/s)		0.1252
Azimuth Resolution (Deg)		14.5

Figure 3-11. Display Parameters – Scene

3.8.3 Chirp/Frame Parameters

When this display tab is selected, the chirp/frame parameters are taken from the actual configuration that was sent to the device and displayed (see [Figure 3-12](#)). In the case of advanced configuration, the values for the different subframes are shown separated by commas for each of the fields.

Profiling	Chirp/Frame	Scene
Start Frequency (Ghz)	77	
Slope (MHz/us)	70	
Samples per chirp	256	
Chirps per frame	32	
Sampling rate (Msps)	5.2090	
Sweep Bandwidth (GHz)	3.4402	
Frame periodicity (msec)	100	
Transmit Antennas	2	
Receive Antennas	4	

Figure 3-12. Display Parameters - Chirp/Frame

3.9 Real-Time Tuning

The "object detection" section from the CONFIGURE tab in past Visualizer releases have been moved to the PLOTS tab to enable real-time tuning of the mmwave processing chain. The effect of these knobs can be seen in real time in the various plots that are displayed. This knob is only available for single profile based legacy frames. When using advanced frame configuration, one could achieve the same functionality via the "Advanced commands" tab. The settings in this tab are reset everytime the user either sends a new complete configuration from CONFIGURE tab or loads a new configuration from a file using "LOAD CONFIG FROM PC AND SEND".

Note

With these controls moving to PLOTS tab, the CONFIGURE tab now carries the default for these commands for the initial configuration of the sensor.

3.9.1 Group Peaks From Same Object

This is a set of checkboxes – one for enabling peak grouping in the range direction and one for enabling peak grouping in the Doppler direction. With the peak-grouping scheme enabled, instead of reporting a cluster of detected neighboring points, only one point, the highest one, is reported. This reduces the total number of detected points per frame. The effect of this can be seen in scatter plots (see [Section 3.9.2](#)).

CLI command details: defines the peakGrouping command.




Figure 3-13. Range Peak Grouping Disabled (Left) and Enabled (Right)

3.9.2 Static Clutter Removal

This check box lets users eliminate static clutter from the scene. Use this option only when trying to detect moving objects in the scene and static objects need to be masked out.

CLI command details: defines the clutter Removal command.

3.9.3 Range Detection Threshold (0 to 100 dB)

This text box lets users enter the threshold for the CFAR (object detection) algorithm in the range direction. Tune this value as per your setup in the radar field of view (for example, clutter, distant object, and so on).

CLI command details: defines the cfarCfg command.

3.9.4 Doppler Detection Threshold (0 to 100 dB)

This text box allows users to enter the threshold for the CFAR (object detection) algorithm in the doppler direction. Tune this value as per your setup in the radar field of view (for example, clutter, distant object, and so on).

3.10 Advanced Commands

This tab allows users to send dynamic commands to the mmwave device while the sensor is running to influence the output of processing chain. The list of commands supported on the device can either be looked up in the [mmWave MCUPLUS SDK User's Guide](#) or by clicking the small help (?) button near the title "Advanced Command". Multiple commands can be typed here before hitting the send command. This tab will be handy to manipulate other parameters of CFAR command (in addition to threshold that is exposed via real time tuning tab), and so forth. When commands are sent using this tab, real time tuning tab is also updated to reflect these new settings.

3.10.1 Special Note About Range and Angle Bias Compensation Configuration

This tab lets users enter the command for the range and angle bias compensation as well. For more information on how to obtain the values for this field, see the [mmWave MCUPLUS SDK User's Guide](#). On receiving this command, the mmWave device corrects the x and y values with the user-supplied bias, but rangeldx (which is the FFT index) is not corrected. In our case, the visualizer GUI handles adjusting the value when rangeldx is converted into the corresponding value in meters for the range profile plot and other heatmaps. If this functionality is not desired, then the command must be given with Range Bias = 0, Rx phase bias set with Real = 0, and Imaginary = 1, for all the applicable virtual antennas (this is also the default from the CONFIGURE tab).

3.11 Plot Settings

This tab allows users to tune the X-Y Scatter plot and Doppler-Range Plot settings.

Scatter Plot Display Time: User can choose to aggregate detected points for multiple consecutive frames (sliding window principle) while displaying on the scatter plot. The time selected by the user in this control (in conjunction with the frame rate) selects number of frames that are aggregated in the sliding window. This setting applies to 2D and 3D scatter plot only. This setting is not valid for advanced frame.

Scatter Plot Colormap: User can set the Colormap for the above two plots based on intensity (SNR) of detected points or the observed doppler of detected points or observed elevation of detected points.

4 Advanced Options

4.1 Load Configuration From PC

Users can configure the device from their own configuration file or the saved app-generated configuration file (see [Section 2.11.2](#)) by using the LOAD CONFIG FROM PC AND SEND button on the PLOTS tab. Ensure the first two commands in this config file are sensorStop followed by flushCfg.

When loading the configuration, using this button will not change the user input knobs in the CONFIGURE tab. If the user wishes to change the configuration loaded using this option, then the user must hand edit the config file while referencing to the *CLI Command* documentation in the [mmWave MCUPLUS SDK User's Guide](#).

The console messages window on the CONFIGURE tab continues to show the progress and feedback of the commands and device interaction even when this option is selected. The description and behavior of the PLOTS tab is similar to what is described in the previous section.

Note

The advanced frame configuration or the range/angle bias measurement procedure can be initiated only by using this button. The configure tab does not provide these capabilities.

4.2 Getting the Version

Users can navigate to Help → About to get the app version that is currently running on the browser. To get the SDK version that is running on the connected mmWave sensor device, send the version CLI command to the device via user UART port or Status Tab as shown below:

```
mmwDemo:/>version
Platform           : AWR294X
RF F/W Version     : 02.04.05.03.22.04.20
RF F/W Patch       : 02.04.06.10.22.09.15
mmWaveLink Version : 02.04.06.06
Die ID Val0 : 2313257
Die ID Val1 : 34
Die ID Val2 = 6, Die ID Val3 = 496
ProcChain          : DDM
mmWave SDK Version : 04.04.00.00
```

The SDK version is shown only when the mmWave sensor device is properly connected to this app using the serial/COM port and a functional demo is running on the target. Checking the version is a good troubleshooting mechanism to determine whether the mmWave device is up and running (see below).

```
*****
Connected device
*****
Retrieving version information ...
Please connect hardware
*****
```

4.3 RCS

This is the small section in the CONFIGURE tab used for calculations and informative purposes.

4.3.1 Desired Radar Cross Section (sq. m)

This text box prompts users to select the desired RCS for getting the Maximum Range at which an object of this RCS is likely to be detected, based on the scene and object detection parameters selected on the left-hand side. Hints for approximate values follow:

- Truck → 100 sq. m
- Car → 10 sq. m
- Motorcycle → 3.2 sq. m
- Adult → 1 sq. m
- Child → 0.5 sq. m

The value for Maximum Range calculated based on this input is shown in the Maximum Range for desired RCS (m) display box.

4.3.2 Maximum Range for Desired RCS (m)

This is for information purposes only to guide users in setting the slider value for Maximum Unambiguous Range accordingly. This value is calculated based on the user input in the Desired Radar Cross Section (sq. m) and the scene and object detection parameters selected on the left-hand side.

4.3.3 RCS at Maximum Unambiguous Range (sq. m)

This is for information purposes only to guide users in setting the slider value for Maximum Unambiguous Range accordingly. This value is calculated based on the user input selected in the Maximum Unambiguous Range and other scene and object detection parameters selected on the left-hand side.

4.4 Concurrent Recording of Processed Stream From mmWave Device

If users want to save the incoming processed stream from the mmWave device for some offline analysis while its getting plotted, they can use the *Record Start* button in the plots tab. The recording can be started while the device is in stopped state and unconfigured (for example, after a fresh reboot and/or the sensor is stopped using the *Sensor Stop* button), or while the device is running and actively outputting data. The data is saved to a timestamped file in binary format on the device. The data keeps accumulating in the file until one of the following conditions are met:

- User presses the Record Stop button
- File size exceeds the limit set in the user-configurable field, File Size Max (MB).
- File accumulated data for at least the time set in the user-configurable field, Record time max(s).

The data saved in this file is the exact same data and format that is transmitted out of the mmWave device over the DATA_port. Users should see the mmWave demo doxygen in the mmWave SDK package to understand the format of the data and how to parse it.

Note

This feature requires the browser version to be at least as mentioned here:
[ti-widget-streamsaver](#).

5 Troubleshooting

5.1 Console Message: Errors Returned by Device

If the user selected invalid parameters in the user generated configuration file or the sliders in the CONFIGURE tab generate an invalid configuration, then the mmWave sensor device reports back an error. This error can be seen as Error -1 in the Console Messages or as a red error message above the SEND CONFIG TO MMWAVE DEVICE button. Users must correct the source of the error (fix the user-generated config file, move the sliders, and so on) and try again. Additionally, if the mmWave device encounters fatal conditions during configuration or realtime, then it communicates back to the user through asserts, and those messages (file and line numbers) are also displayed in the Console Messages window. Because these are fatal conditions, user must browse to that file and line number to understand the cause for the error. To recover from this, users must reboot the mmWave device, connect the ports using the Visualizer, and perform reconfiguration.

5.2 Serial Port Status Message: Not Switching to Hardware Connected or Both Ports Are Not Showing Up

A successful connection results in two COM ports displaying in the bottom status bar, and a Hardware Connected (mmWave SDK 3.4 or later) or "Waiting for Data.." message for the DATA_port (mmWave SDK 3.3 or earlier) .

If the user does not see the previous message, then the following common errors could be the root cause:

- The mmWave device is not powered on and running the demo
- Incorrect COM port numbers were selected in Options → Serial port.
- Another application (for example, Tera Term) has those COM ports open and the app is unable access to these ports.
- The device was just rebooted while the app was running.

Once previously mentioned errors are corrected, use the small icon (a broken link or exclamation icon) at the bottom of the screen to disconnect and connect the ports again.

5.3 Console Message: sensorStart Message Not Sent to Host

If the user sees some messages appear in the console messages, but not all of them and the last message is not sensorStart, then the following common errors could be the root cause:

- Commands sent earlier generated an error. User must correct the source of error (fix the user-generated configuration file, move the sliders, and so on) and try again.
- Commands sent earlier caused the software running on the device to crash and an assert or exception message is displayed. Users can connect the Code Composer Studio™ (CCS) debugger to the target device to debug this situation further. In the absence of CCS, reboot the device and start again. If the device still does not work for a given config, check the config against the [mmWave MCUPLUS SDK User's Guide](#).
 - One reason could be that the number of plots selected caused the shipment of the output data to exceed one frame duration.
- Sometimes the UART on the target device does not receive all the characters or messages (for example, the PC sends configuration data over the UART faster than the device can process). Just repeat the action (Send Config.. or Load Config..) and try again.

5.4 Warning for Plots and Frame Rate

The following are some guidelines for selecting the plots and frame rate:

- If heatmap is selected, reduce the frame rate to less than 5 fps. (If this suggestion is not followed, then the target mmWave device intentionally halts and the user must reboot the device).
- If heatmap is not selected but all other plots are selected, then depending on the scene parameters selected, the GUI performance can be sluggish and the user should ideally select 10 fps as the frame rate.

User should select the following baud rates for DATA_port in the "Serial port" dialog using custom values when using mmW demo from mmWave_mcuplus_SDK as For SDK version <= 4.3, use 852272 for AWR294X and 892857 for AM273X. For SDK version >= 4.4, use 3125000 for both AWR294X and AM273X.

5.5 Configuration Successful, but Plots Not Updating

One of the commands sent caused the software running on the device to crash and an assert or exception message is displayed in the console messages. Users can connect the CCS debugger to the target device to debug this situation further. In the absence of CCS, reboot the device and start again. If the device still does not work for a given config, check the config against the [mmWave MCUPLUS SDK User's Guide](#). One reason could be that the number of plots selected caused the shipment of the output data to exceed one frame duration.

Another reason could be the mismatch between the baud rate selected for DATA_port in the Visualizer versus the rate at which the device is transmitting (mmWave SDK 4.x). To address this, reboot the sensor or stop the sensor, re-connect the serial ports from Visualizer GUI with desired baud rate and reconfig the sensor.

6 Customizing the mmWave Demo Visualizer

Users can login to the [gallery](#), locate the Visualizer app tile, and click the *Import to the GUI composer* icon, to import the application in their GC workspace. Beyond this, users have access to GUI composer resources to customize the demo according to their needs. A quick overview of the mmWave Demo Visualizer specific files follows:

- mmWave.js: Main file that communicates with the GUI composer framework, communicates to the mmWave device using the configured COM ports, processes GUI-generated actions, and plots the data generated by the mmWave device
- input_validations.js: validates the CLI configuration before it is sent to the mmWave device
- dynamic_tuning.js: implementation of "real time tuning" tab and "advanced commands" tab
- input.js: Handles all the backend computations behind the CONFIGURE tab
- Index.gui: Auto-generated file that handles the layout of the Visualizer app
- Helper utilities: Delaunay.js, fft.js, math.js, math_griddata.js, and myutil.js

Useful references follow:

- [GUI Composer Getting Started](#)
- [GUI Composer User's Guide](#)

Revision History

Changes from Revision * (November 2021) to Revision A (March 2023)	Page
• Updated Abstract in this document.....	1
• Updated the numbering format for tables, figures and cross-references throughout the document.....	3
• Updated Section 1.3	3
• Updated Section 2.11.2	10
• Updated Section 3.9.4	20
• Updated Section 3.10	20
• Updated Section 4.1	21
• Updated Section 4.2	21
• Updated Section 5.4	23
• Updated Section 5.5	24

IMPORTANT NOTICE AND DISCLAIMER

TI PROVIDES TECHNICAL AND RELIABILITY DATA (INCLUDING DATA SHEETS), DESIGN RESOURCES (INCLUDING REFERENCE DESIGNS), APPLICATION OR OTHER DESIGN ADVICE, WEB TOOLS, SAFETY INFORMATION, AND OTHER RESOURCES "AS IS" AND WITH ALL FAULTS, AND DISCLAIMS ALL WARRANTIES, EXPRESS AND IMPLIED, INCLUDING WITHOUT LIMITATION ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT OF THIRD PARTY INTELLECTUAL PROPERTY RIGHTS.

These resources are intended for skilled developers designing with TI products. You are solely responsible for (1) selecting the appropriate TI products for your application, (2) designing, validating and testing your application, and (3) ensuring your application meets applicable standards, and any other safety, security, regulatory or other requirements.

These resources are subject to change without notice. TI grants you permission to use these resources only for development of an application that uses the TI products described in the resource. Other reproduction and display of these resources is prohibited. No license is granted to any other TI intellectual property right or to any third party intellectual property right. TI disclaims responsibility for, and you will fully indemnify TI and its representatives against, any claims, damages, costs, losses, and liabilities arising out of your use of these resources.

TI's products are provided subject to [TI's Terms of Sale](#) or other applicable terms available either on [ti.com](https://www.ti.com) or provided in conjunction with such TI products. TI's provision of these resources does not expand or otherwise alter TI's applicable warranties or warranty disclaimers for TI products.

TI objects to and rejects any additional or different terms you may have proposed.

Mailing Address: Texas Instruments, Post Office Box 655303, Dallas, Texas 75265
Copyright © 2023, Texas Instruments Incorporated